

# Configure Exchange ActiveSync Access to Exchange Labs

These procedures show you how to configure a Windows Mobile device to access your Exchange Labs mailbox. You can only synchronize your mobile device with one Exchange Labs mailbox. When you configure your Windows Mobile device to synchronize with your Exchange Labs mailbox, an Exchange ActiveSync mailbox policy will be applied to your device. This policy makes it possible for you to perform a remote wipe on your mobile device. For more information about Microsoft Exchange ActiveSync mailbox policies and remote device wipe, see the next section.

You can also enable your Exchange Labs mailbox to receive voice mail messages from your mobile device. For more information, see [Configuring Voice Mail](#).

Configure Exchange ActiveSync on a Windows Mobile 6.0 Phone

1. On the mobile device, from the home screen, click **Start**, and then click **ActiveSync**.
2. Click **Menu**, and then click **Configure Server**.
3. Enter the server address. The server address is [m.outlook.com](http://m.outlook.com).
4. Select the **This server requires an encrypted (SSL) connection** check box.
5. Click **Next**.
6. Enter your user name, password, and domain.
7. Select the **Save password** check box.
8. Click **Next**.
9. Select the check box next to each type of information that you want to synchronize with the server, and then click **Finish**.

Configure Exchange ActiveSync on a Windows Mobile 5.0 Phone

1. On the mobile device, from the home screen, click **Start**, and then click **ActiveSync**.
2. Click **Menu**, and then click **Configure Server**.
3. Enter the server address. The server address is [m.outlook.com](http://m.outlook.com).
4. Select the **This server requires an encrypted (SSL) connection** check box.
5. Click **Next**.
6. Enter your user name, password, and domain. The user name should include your name, the at (@) symbol, and your domain name, for example, [tony@contoso.com](mailto:tony@contoso.com).
7. Select the **Save password** check box.
8. Click **Next**.
9. Select the check box next to each type of information that you want to synchronize with the server, and then click **Finish**.

## **Note:**

The server address for configuring synchronization has changed from [BL2PRD0001.prod.exchangelabs.com](http://BL2PRD0001.prod.exchangelabs.com) to [m.outlook.com](http://m.outlook.com). For information about how to change your server address, see [Change Your Exchange Labs Mobile Phone Settings](#).